



RUNNING LIGHT DATA PATTERN

Protocol: MQTT

Every One-Minute Data from Device Data Pattern:

- Device_id:deviceId:Intensity:device_status:Power:Temperature:Autobrightness:AutoMotion:Lux

```
{device_id:tubeF1F2F3:8:1:3.76:32.37:1:1:791}
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/status, message_id : , length : 64, Raw payload : 12310010111810599101951051005811611798017049705070515856584958514655545851504651555849584958555749125
```

Response on 200:

- device_id:300:Intensity:device_status:Power:Temperature:Autobrightness:AutoMotion:Lux

```
{device_id:300:8:1:3.76:32.45:1:1:791}
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/status, message_id : , length : 57, Raw payload : 123100101118105991019510510058514848586584958514655545851504652535849584958555749125
```

To Update the Intensity:

- Send data in below Format,
 - autoBrightness:0:Intensity

Ex. autoBrightness:0:10

```
autoBrightness:0:10
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/control, message_id : , length : 39, Raw payload : 97117116111661141051031041161101011151155848584948
```

To set the AutoBrightness:

- Send data in below Format,
 - autoBrightness:1:Lux

Ex. autoBrightness:1:600



```
autoBrightness:1:700
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/control, messageid : , length : 40, Raw payload : 9711711611166114105103104116110101115115584958554848
```

To set the Threshold Temperature:

- Send data in below Format,
 - tempOverThreshold:temperature
 - Exa: tempOverThreshold:70
 - Note: Default set value is 80.
 - Once the threshold is updated you will get the response on MQTT for conformation as below,

```
{device_id:tubeF1F2F3:tempOverThresholdValueUpdated: 30}
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/status, messageid : , length : 75, Raw payload : 12310010111810599101951051005811611798017049705070515811610110911279118101114841041141011151041111081008697108117101851121009711610110058325148125
```

To Set the Maximum Analog Value:

- Send Data in the below Format,
 - maxAnalogPulseDutyCycle:Value
 - Exa: maxAnalogPulseDutyCycle:250
 - Note: Default set value is 204
 - Once the threshold is updated you will get the response on MQTT for conformation as below,

```
{device_id:tubeF1F2F3:maxAnalogPulseDutyCycleUpdated: 204}
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/status, messageid : , length : 77, Raw payload : 1231001011181059910195105100581161179801704970507051581099712065110971081111038011710811510168117116121671219910810185112100971161011005832504852125
```

To update Global Topic:

- Send Data in the below Format,
 - updateMqttTopic:globalTopic:topic
 - Note: The default set topic is evoluznGlobal, and this topic's maximum string length can be 20.
 - Once the threshold is updated you will get the response on MQTT for conformation as below,



```
{device_id:tubeF1F2F3:GlobalTopicUpdated: tubeGlobal}
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/status, mess  
ageld : , length : 72, Raw payload : 12310010111810599101951051005811611798  
017049705070515871108111989710884111112105998511210097116101100583  
211611798101711081119897108125
```

To check the Stored Data:

- Send Data in the below Format,
 - storeStatus
 - This command checks all internal EEPROM parameters stored in the device,
 - Format is,
 - {device_id:deviceID:GLOBAL TOPIC:TEMPERATURE THRESHOLD:MAX ANALOG VALUE:MOTION COUNTER:PIR SENSOR DATA:USER DEFINED LUX}

```
{device_id:tubeF1F2F3:tubeGlobal:30:204:25:483855:700}
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/status, mess  
ageld : , length : 73, Raw payload : 123100101118105991019510510058116117981  
017049705070515811611798101711081119897108585148585048525850535852565  
156535358554848125
```

To restart the Device:

- Send the Data in below Format:
 - Restart

Payload

```
restart
```

Over Temperature Alerts will publish Every One Minute interval if temperature is above Threshold temperature:

```
{device_id:tubeF1F2F3:Device Internal Temperature > 30}
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/status, mess  
ageld : , length : 74, Raw payload : 123100101118105991019510510058116117981  
017049705070515868101118105991013273110116101114110971083284101109112  
101114971161171141013262325148125
```

To update the Motion Counter:

- Send data in below Format:
 - motionCounter:value
Ex. motionCounter:50
 - Note: Default set value is 25.
 - Once the counter is updated you will get the response on MQTT for conformation as below,



```
{device_id:tubeF1F2F3:motionCounterUpdated: 25}
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/status, mess  
ageld : , length : 66, Raw payload : 12310010111810599101951051005811611798  
017049705070515810911111610511111067111117110116101114851121009711  
610110058325053125
```

To set the autoMotion ON:

- Send data in below Format:
 - autoMotionDetection:100
 - Once the auto motion ON you will get the response on MQTT for conformation as below,

```
{device_id:tubeF1F2F3:autoMotionActivate}
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/status, mess  
ageld : , length : 60, Raw payload : 12310010111810599101951051005811611798  
017049705070515897117116111771111161051111106599116105118971161011  
25
```

To set the autoMotion OFF:

- Send data in below Format:
 - autoMotionDetection:0
 - Once the auto motion OFF you will get the response on MQTT for conformation as below,

```
{device_id:tubeF1F2F3:autoMotionDeactivate}
```

```
qos : 0, retain : false, cmd : publish, dup : false, topic : tubeF1F2F3/status, mess  
ageld : , length : 62, Raw payload : 12310010111810599101951051005811611798  
017049705070515897117116111771111161051111106810197991161051189711  
6101125
```